

Loading and Unloading Data from CoCo










https://help.go-ci.com/ Printed on 2025/09/01 04:28



- 1. First Connect your CoCo device by ethernet to your PC.
- In VDS, click Data Collector > in the Devices menu, click Load > Click CoCo device > Select the Device you are using > Click Next > Click Load Factories and Routes > Click Next
- 3. Your VDS will have Factories and Routes to choose to upload to your CoCo device. **Select options to upload >** Click **Upload >** Click **Finish**

To Unload, follow the same steps from above after clicking **Unload** from the **Devices** menu.

From:
https://help.go-ci.com/ - Crystal Instruments Help

Permanent link:
https://help.go-ci.com/vds:transfer

Last update: 2024/12/20 20:39