
Loading and Unloading Data from CoCo



- 1. First Connect your CoCo device by ethernet to your PC.
- In VDS, click Data Collector > in the Devices menu, click Load > Click CoCo device > Select the Device you are using > Click Connect and then Next > Click Load Factories and Routes > Click Next
- 3. Your VDS will have Factories and Routes to choose to upload to your CoCo device. **Select options to upload >** Click **Upload >** Click **Finish**

To Unload, follow the same steps from above after clicking **Unload** from the **Devices** menu.

From:

https://help.go-ci.com/ - Crystal Instruments Help

Permanent link:

https://help.go-ci.com/vds:transfer?rev=1734726767

Last update: 2024/12/20 20:32